


Release Notes

Artista Device Finder

ADF

Find and Configure DATA DISPLAY Devices in the Network



Version 1.4.1
25.10.2024

FORTEC
UNITED STATES



FORTEC
INTEGRATED



FORTEC
UNITED KINGDOM



The information contained in this document has been carefully researched and is, to the best of our knowledge, accurate. However, we assume no liability for any product failures or damages, immediate or consequential, resulting from the use of the information provided herein. Our products are not intended for use in systems in which failures of product could result in personal injury. All trademarks mentioned herein are property of their respective owners. All specifications are subject to change without notice.

Table of Contents

1	Revision History	3
2	Artista Device Finder (ADF) Release History	3
2.1	Version 1.0.0	3
2.2	Version 1.2.0	3
2.3	Version 1.4.0	4
2.4	Version 1.4.1	4
3	Known Issues of latest Artista Device Finder (ADF) Version	5
3.1	First device scan may trigger Windows Firewall to popup Windows Security Alert message	5
4	News and Updates	5

1 Revision History

Date	Version	Description	Page
07.12.2011	1.0.0	Initial version for ADF release 1.0.0	All
12.04.2012	1.2.0	Updated for new ADF release 1.2.0	3
15.05.2024	1.4.0	Update for new ADF release 1.4.0	1,2,3,5,6,7
10.10.2024	1.4.1	Update for new ADF release 1.4.1	2,3,5,4
25.10.2024	1.4.1	Update cover template	all

2 Artista Device Finder (ADF) Release History

This section lists all software releases for Artista Device Finder (ADF).

2.1 Version 1.0.0

Exact software version: 1.0.0
Release date: 08.12.2011

This is the initial release for the Windows software Artista Device Finder (ADF).

It supports network setup on the following devices:

- ArtistaNET-III with firmware version 5.6.0
- DigiPoster-III with firmware version 1.8.0
- VideoPoster-II with firmware version 2.2.0
- VideoPoster-III with firmware version 1.0.0

2.2 Version 1.2.0

Exact software version: 1.2.0.34632
Release date: 12.04.2012

New features:

- Supports authentication required by devices with new firmware to change the network settings. Authentication is required by the following devices:
 - ArtistaNET-4.3 with firmware version 1.8.0 and above
 - DigiPoster-4.3 with firmware version 1.6.0 and above
 - VideoPoster-III with firmware version 1.2.0 and above
- Devices in the table can be sorted by clicking on column headers
- Selected devices in the table can be exported as connections for Acc 3 (export to a file which can be imported in the connections dialog of Acc 3)

Changes:

- Application behaves as single application now (no second instance can be started, already started instance receives focus instead)

Fixes:

- Fixed installation problems on some systems

2.3 Version 1.4.0

Exact software version: 1.4.0
Release date: 15.05.2024

New features:

- Supports authentication required by devices with new firmware to change the network settings. Authentication is required by the following devices:
 - VideoPoster-IV
 - VideoPoster-M4
 - WebPoster-M3
 - WebPoster-M4

Changes:

- Upgrade to MVS2022
- Upgrade QT library to QT5.15.16
- Update Company name and logo from Distec to FORTEC Integrated

Fixes:

None

2.4 Version 1.4.1

Exact software version: 1.4.1
Release date: 10.10.2024

New features:

- Add device status when available

Changes:

- Rename some devices information in the first row
- Update ACC name to ACC4
- Update devices firmware versions

Fixes:

None

3 Known Issues of latest Artista Device Finder (ADF) Version

This section lists all known issues of the latest Artista Device Finder (ADF) software version.

3.1 First device scan may trigger Windows Firewall to popup Windows Security Alert message

This does not impact application performance.

4 News and Updates

The latest version of documents, drivers and software packages can be found at:

German Site <https://www.fortec-integrated.de/service/downloads/>

English Site <https://www.fortec-integrated.de/en/service/downloads/>

Our company network supports you worldwide with offices in Germany, Austria, Switzerland, the UK and the USA. For more information please contact:

Headquarters

Germany



FORTEC
GROUP

FORTEC Elektronik AG

Augsburger Str. 2b
82110 Germering

Phone: +49 89 894450-0

E-Mail: info@fortecag.de

Internet: www.fortecag.de

Fortec Group Members

Austria



FORTEC
INTEGRATED

FORTEC Integrated GmbH Office Vienna

Nuschinggasse 12
1230 Wien

Phone: +43 1 8673492-0

E-Mail: info@fortec-integrated.de

Internet: www.fortec-integrated.de

Germany



FORTEC
INTEGRATED

FORTEC Integrated GmbH

Augsburger Str. 2b
82110 Germering

Phone: +49 89 894363-0

E-Mail: info@fortec-integrated.de

Internet: www.fortec-integrated.de

Switzerland



FORTEC
SWITZERLAND

FORTEC Switzerland AG

Bahnhofstraße 3
5436 Würenlos

Phone: +41 44 7446111

E-Mail: info@fortec.ch

Internet: www.fortec.ch

United Kingdom



FORTEC
UNITED KINGDOM

FORTEC Technology UK Ltd.

Osprey House, 1 Osprey Court
Hinchingsbrooke Business Park
Huntingdon, Cambridgeshire, PE29 6FN

Phone: +44 1480 411600

E-Mail: info@fortec.uk

Internet: www.fortec.uk

USA



FORTEC
UNITED STATES

FORTEC US, Corp.

87 Raynor Avenue, Unit 1
Ronkonkoma, NY 11779

Phone: +1 631 5804360

E-Mail: info@fortec.us

Internet: www.fortec.us